

Masternode Guide:

wget <http://www.motilecoin.io/Motiled>

1. For start Masternode first of all add require data in config file. www.motilecoin.io/Motile.conf

Login to Server than put command : ls

Now you can show daemon like : Motiled

2. For masternode start you have to send Exact require coin (Masternode collateral) in that server address.

For that first of all start daemon by this command. : ./Motiled

As your daemon start next you have to get address for send coin which is require for masternode

For that write this command. : ./Motiled getaddressesbyaccount ""

Press enter so you will get one address

Copy that address and send require Exact coin in that address for start masternode (Masternode Collateral).

3. After send coin you have to check whether your coin receive or not.

For that write this command. : ./Motiled getinfo

After enter this command you can check balance. If you get require coin in balance that is ok.

If you did not get coin in balance than again type same command after some seconds.

When you get balance than you can do next step.

4. For start masternode you have to copy masternode genkey. For that enter this command. : ./Motiled masternode genkey

press enter so you got gen key. copy that gen key.

5. Next step you have to edit Config file.

For that first of all stop daemon by this command.: `./Motiled stop`

6. Now,For edit config file write command : `sudo nano ~/.Motive/Motive.conf`

Press Enter.

7.Now you can see config file in your terminal.

Go to last line and paste below three line.

```
masternode=1
```

```
masternodeprivkey=<paste your genkey>
```

```
(ex.masternodeprivkey=aEdh202kjhkbKHJs5...).
```

```
masternodesoftlock=1
```

press `ctrl+x`. now press `Y` and enter so you go to return in main terminal.

8. Now you can start masternode.

For that first of all you have to start daemon. For that write this command.: `./Motiled`

Press enter so your daemon start now.

9. Now for start masternode write this command. : `./Motiled masternode start`

Press enter so you will get message like your masternode will start after 15 confirmations.

If you got message like this, that is right. So your masternode will start after 15 Confirmations.

10.When 15 confirmation got than you enter last command again. : `./Motiled masternode start`

Press enter and you got message like Your masternode successfully start.

That's all.